



JPOS Driver for Fujitsu Cash Drawer

Fujitsu Cash Drawer Driver Release Notes (SUSE Linux Version)

Document Revision 1.0

Document Change History

Date	Revision	Description
12-07-2018	1.0	Initial Release

Scope

- GUI Cash Drawer Test Utility
- Silent installer

Deliverables

- Fujitsu32.tar.gz
- Fujitsu64.tar.gz
- install.sh
- Release_Notes.pdf

Supported Operating Systems

- SUSE Linux Enterprise Server (SLES) 11 SP3 32-Bit
- SUSE Linux Enterprise Server (SLES) 11 SP3 64-Bit
- SUSE Linux Enterprise Server (SLES) 11 SP4 64-Bit
- SUSE Linux Enterprise Desktop (SLED) 12 SP3 64-Bit

Requirements

- Installer requires Super User / Root privileges
- JAVA_HOME environment variable must be set
- The following Patterns must be installed:
 - Base Development
 - C/C++ Development
 - Linux Kernel Development
- Java Virtual Machine (JVM) 1.6 or higher

Usage

- `./install.sh [INSTALL_DIR]`
 - `INSTALL_DIR` is optional. It is used to install the driver to a directory other than the default.
 - Example: `./install.sh /home/drivers`
- Default installation directory (if `INSTALL_DIR` is left blank) = `/opt`

Installation Steps

- 1) Copy all files listed under Deliverables to the target computer.
- 2) On the target computer, change to the directory where the files were copied.
- 3) Type the following command (see usage):
 - a) `sudo -E ./install.sh`
- 4) Enter the SUDO password.
- 5) The application will be installed to the following location:
 - a) `[INSTALL_DIR]/Fujitsu/JavaPOS`
 - b) For example, if installed to Default directory, the full path of the installed application is `/opt/Fujitsu/JavaPOS`
- 6) Change directory to the installed application.
- 7) Type the following command to execute the test application:
 - a) `./POSTest.sh`

Note: If the application already exists in the `INSTALL_DIR`, it will be backed up and then the installation will continue.

Note: A log file will be created in the directory where the installation was executed.