


Graphics Driver V02L03 Installation Guide for PC (Coral-P/PA PCI Card)

Aug 21, 2006

1. Login by Administrator authority.
2. Perform the following installation programs and do work according to the screen displayed.

Installation program: MB8629xDrv_V02L03PC.exe

3. When the password is requested, enter “scarlet” in lowercase characters.



4. Follow the instructions on your screen.
5. If “digital signature was not found” or “installation of hardware” or “installation of software” dialog is displayed, click “OK” or “continue” button.
6. After installation, you will need to reboot the PC.

Note:

“Graphics Driver” has been verified to work on the following operating systems:

- Microsoft Windows NT Workstation 4.0 SP6
- Microsoft Windows 2000 Professional SP3/SP4
- Microsoft Windows XP Professional SP1