Windows Security Update Information for PRIMERGY TX200FT S2

This list contains the security updates which are released on Windows Update site or Microsoft Update site, and require attention at installation into PRIMERGY TX200FT S2.

1. Confirm the release dates of security updates which you will install. If this list is earlier than one or more security updates, please check again http://www.fujitsu.com/global/services/computing/server/ia/driver/ for the latest information.

Last Modified: Dec. 14, 2011

2. Check whether each update is in this list or not. Any updates which there are in this list, refer [Description] before installing. You can install any updates which are NOT in this list, without any preparation.

The following updates can occur serious trouble on PRIMERGY TX200FT S2 system. Please refer the [Description] before appling Windows Update (or Microsoft Update). If there exists some requirement, then perform it before install each update, otherwise do never install the update.

* The other updates on Windows Update (or Microsoft Update), issued before this list was modified, are available to install.

Microsoft Security Bulletin Number	Knowledge Base Article Number	Severity Rating	Title	To Install on		Preinstalled	Checked on	Description
				CoServer	Virtual Server	1 icinstaneu	(mm/dd/yyyy)	Description
MS11-098	2633171	Important	Security Update for Windows Server 2003	NG	NG	NO	Dec/14/2011	Vulnerability in Windows Kernel Could Allow Elevation of Privilege Do not install this Update. (*1)
MS11-011	2393802	Important	Security Update for Windows Server 2003	NG	NG	NO	Feb/09/2011	Vulnerabilities in Windows Kernel Could Allow Elevation of Privilege Do not install this Update. (*1)
MS10-021	979683	Important	Security Update for Windows Server 2003	NG	NG	NO	Apr/14/2010	Vulnerabilities in Windows Kernel Could Allow Elevation of Privilege Do not install this Update. (*1)
MS10-015	977165	Important	Security Update for Windows Server 2003	NG	NG	NO	Feb/10/2010	Vulnerabilities in Windows Kernel Could Allow Elevation of Privilege Do not install this Update. (*1)
MS09-058	971486	Important	Security Update for Windows Server 2003	NG	NG	NO	Oct/14/2009	Vulnerabilities in Windows Kernel Could Allow Elevation of Privilege Do not install this Update. (*1)
MS09-012	956572	Important	Security Update for Windows Server 2003	NG	NG	NO	Apr/15/2009	Vulnerabilities in Windows Could Allow Elevation of Privilege. Do not install this Update. (*1)
MS08-064	956841	Important	Security Update for Windows Server 2003	NG	NG	NO	Oct/15/2008	Vulnerability in Virtual Address Descriptor Manipulation Could Allow Elevation of Privilege. Do not install this Update. (*1)
MS07-022	931784	Important	Security Update for Windows Server 2003	OK available only on W2k3 SP1	OK available only on W2k3 SP1	NO	Apr/11/2007	Vulnerability in the Windows kernel could allow elevation of privilege Before installing this Security Update, install Windows Server 2003 Service Pack 1. If no Windows Service Pack is installed, KB931784 causes fail to synchronize the virtual servers. * Windows Server 2003 Service Pack 2 cannot be installed on PRIMERGY FTmodel.
-	-		Intel -Networking -Intel® PRO/1000 MT Dual Port Server Adapter	NG	NG	NO	Apr/11/2007	Do not install a driver by Windows Update.
-	914961		Windows Server 2003 Service Pack 2	NG	NG	NO	Apr/04/2007	Do not install Windows Server 2003 Service Pack2 on PRIMERGY FTmodel.
-	-	-	Intel(R) PRO/1000 MT Desktop Adapter - released in April, 2006	NG	NG	NO	Oct/02/2006	Do not install a driver by Windows Update.

(*1) Before install this update, check no QFE branch module of Windows kernel to be applied:

- 1. Click [Start], click [Run], type "C:\WINDOWS\system32" into the [Open] text box, and click [OK].
- 2. Right-click [ntoskrnl.exe], and then click [Properties].
- 3. On the [Version] tab, click [File version] in the [Other version information] area.
- 4. If the value includes "qfe", do not install this update. Otherwise, it can be applied.